



建立 Windows 11 作業系統密碼 (1)

- 點選下方「Windows」鍵，並選擇「設定」。




建立 Windows 11 作業系統密碼 (2)

- 選擇右方列「帳戶」後，再選擇「登入選項」



建立 Windows 11 作業系統密碼 (3)

- 選擇「密碼」登入後，點選「新增」。



建立 Windows 11 作業系統密碼 (4)

- 密碼長度建議6~10碼，且需由英文字母(含大寫或小寫)與數字組合而成。

← 變更您的密碼

新密碼

確認密碼

密碼提示


下一步 取消

完成 取消

輸入及確認「新密碼」並按「下一步」後，按「完成」即可完成密碼之建立。

【本機安全性原則】之設定 (1)

- 桌面下方搜尋欄輸入「本機安全性原則」，再點選上方「以系統管理員身分執行」。



【本機安全性原則】之設定 (2)

- 安全性設定\帳戶原則\密碼原則
 - 密碼必須符合複雜性需求：已啟用
 - 密碼最長使用期限：180天
 - 密碼最短使用期限：1天
 - 強制執行密碼歷程記錄：3記憶的密碼
 - 最小密碼長度：8個字元


本機安全性原則

檔案(F) 動作(A) 檢視(V) 說明(H)

原則	安全性設定
使用可還原的加密來存放密碼	已停用
放鬆最小密碼長度限制	尚未定義
密碼必須符合複雜性需求	已啟用
密碼最長使用期限	180
密碼最短使用期限	1 天
強制執行密碼歷程記錄	3 記憶的密碼
最小密碼長度	8 個字元
最小密碼長度稽核	尚未定義

【密碼永久有效：取消】之設定 (1)

- 桌面下方搜尋欄輸入「電腦管理」，再點選上方「以系統管理員身分執行」。



【密碼永久有效：取消】之設定 (2)

- 點選系統工具/本機使用者和群組/使用者
- 點選目前使用的帳號 (每台電腦都不一樣)

The screenshot shows the Windows System Management console. On the left, the tree view is expanded to '本機使用者和群組' (Local Users and Groups) > '使用者' (Users). The 'User' folder is selected. In the center pane, the 'User' account is selected. On the right, the '設定檔' (Profile) tab is active, showing the 'User' profile. The '密碼永久有效(P)' (Password never expires) checkbox is unchecked and highlighted with a red box. A red arrow points from this checkbox to the '套用(A)' (Apply) button at the bottom right, which is also highlighted with a red box. The text '取消打勾' (Uncheck) is written in red next to the checkbox. Other options like '使用者必須在下次登入時變更密碼(M)' and '使用者不能變更密碼(C)' are also visible but not highlighted.